

PepMute™ siRNA Transfection Reagent



10075 Tyler Place, Suite 19
 Ijamsville, MD 21754
 FAX. 301-560-4919
 TEL. 301-330-5966
 Toll Free. 1-(866)-918-6812
 Email: info@signagen.com
 Web: www.signagen.com

----- A Standard Protocol for siRNA
 Transfection of Mammalian Cells

- 100 μ l
- 500 μ l
- 1000 μ l

This product is for laboratory research ONLY and not for diagnostic use

Introduction:

PepMute™ siRNA Transfection Reagent is a novel peptide based siRNA delivery tool which provides more than 95% silencing efficiency at 1 nM siRNA in variety of mammalian cells. With our proprietary peptide simulation technology (PST), PepMute™ reagent was identified and validated as an exceptionally efficient vector for condensing and transfecting short (under 100 bp) single or double stranded nucleic acids such as siRNA, miRNA mimics and DNA oligos to wide spectrum of mammalian cells.

Important Guidelines for Transfection:

- PepMute™ reagent was formulated as a powerful siRNA delivery tool. For most adherent cell lines and primary cells, siRNA at 1.0 ~5 nM is basically sufficient to obtain up to 90% gene silencing, as observed for Hela, MCF and NIH-3T3. For hard-to-transfect cells, we recommend using a final siRNA concentration of 20 nM.
- While the standard protocols for siRNA transfection and siRNA/DNA co-transfection are being given below, optimization is often needed for maximal gene silencing.

PART I. Standard siRNA Transfection

Step I. Preparation of Working Solution of PepMute™

Transfection Buffer:

PepMute™ Transfection Buffer (5x) is provided as 5x concentrated stock solution. To make working solution, dilute one part of the stock solution with 4 parts of ddH₂O into a sterile bottle. The working solution is stable at 4 °C~RT for 12 months.

Step II. Cell Seeding:

Cells should be plated 18 to 24 hours prior to transfection so that the monolayer cell density reaches to the optimal ~50% confluency at the time of transfection. Complete culture medium with serum and antibiotics is freshly added to each well 30~60 minutes before transfection.

Note: PepMute™ reagent is NOT interfered by serum and antibiotics, therefore serum and antibiotic containing medium can be used during the entire experiment.

Table 1. A Guideline for siRNA transfection per cell culture vessel

Culture Dish	Growth Medium (ml)	Transfection Buffer (μ L)	siRNA (pmols) Final 5.0 or 20 nM	PepMute™ Reagent (μ L)
24-well	0.5	50	2.5 / 10	1.2
12-well	0.75	75	3.75 / 15	1.9
6-well	1.0	100	5.0 / 20	2.4
60 mm	3.0	300	15 / 60	7.2
10 cm / Flask 75	8.0	800	40 / 160	20

Step III. siRNA Transfection Protocol:

For optimal siRNA-mediated silencing, we recommend using 1~20 nM siRNA. As a starting point, we recommend using 5.0 nM siRNA which usually gives satisfactory silencing result for most adherent cell lines or primary cells. For hard-to-transfection cells, we recommend using a final siRNA concentration of 20 nM. (bold & underlined in **Table 1**). Due to the exceptional siRNA condensing capacity of PepMute™ reagent, we recommend using same amount of PepMute™ reagent for final 1~20 nM of siRNA (**Table 1**).

The following conditions are given per well in a 6 well plate. For other culture format, please refer to **Table 1**.

- For each well, add 1.0 ml of complete medium with serum and antibiotics freshly 30~60 minutes before transfection.
- Dilute 5.0 or **20** pmoles siRNA (final concentration of 5.0 or **20** nM respectively per well) into 100 μ l of working solution of PepMute™ Transfection Buffer prepared in **Step I**. Vortex to mix followed by brief spin to bring drops to the bottom of the tube.

Note: For maximum gene silencing, dilute siRNA and PepMute™ reagent with PepMute™ Transfection Buffer (1x).

We strongly suggest reconstituting siRNA stock solution at 5.0 μ M, so add 1.0 or 2.0 μ l siRNA stock solution per well of 6-well plate to make final 5.0 and 10 nM siRNA respectively.

- Add 2.4 μ l PepMute™ reagent, mix by pipetting up and down.
- Incubate for ~15 minutes at RT to let transfection complex form.
- Note: Never keep the complex longer than 30 minutes.**
- Add the transfection mix to the cells drop wise. Gently rock the plate back and forth and return the plate to CO₂ incubator.
- Gene silencing is usually measured 24~48 hours post transfection.

PART II. A Standard Protocol for DNA/siRNA Co-transfection

Step I. Preparation of Working Solution of PepMute™ Transfection Buffer:

PepMute™ Transfection Buffer (5x) is provided as 5x concentrated stock solution. To make working solution, dilute one part of the stock solution with 4 parts of

PepMute™ siRNA Transfection Reagent



10075 Tyler Place, Suite 19
Ijamsville, MD 21754
FAX. 301-560-4919
TEL. 301-330-5966
Toll Free. 1-(866)-918-6812
Email: info@signagen.com
Web: www.signagen.com

----- A Standard Protocol for siRNA/DNA
Co-transfection of Mammalian Cells

- 100 µl
- 500 µl
- 1000 µl

This product is for laboratory research ONLY and not for diagnostic use

ddH₂O into a sterile bottle. The working solution is stable at 4 °C~RT for 12 months.

Step II. Cell Seeding:

Cells should be plated 18 to 24 hours prior to transfection so that the monolayer cell density reaches to the optimal ~70% confluency at the time of transfection. Complete culture medium with serum and antibiotics is freshly added to each well 30~60 min before transfection.

Note: PepMute™ reagent is NOT interfered by serum and antibiotics, therefore serum and antibiotic containing medium can be used during the entire experiment.

Table 2. A Guideline for DNA & siRNA Co-transfection Per Cell Culture Vessel

Culture Dish	Growth Medium (ml)	Transfection Buffer (µL)	Plasmid DNA (µg)	siRNA (pmols) Final 5.0 nM	PepMute™ Reagent (µL)
24-well	0.5	50	0.25	2.5	1.5
12-well	0.75	75	0.375	3.25	2.25
6-well	1.0	100	0.5	5.0	3
60 mm	3.0	300	1.5	15	9
10 cm / flask 75	8.0	800	4.0	40	24

Step III. DNA & siRNA co-transfection protocol:

For DNA/siRNA co-transfection experiment, we recommend using 0.5~0.6 µg DNA and 1~10 nM siRNA per well in a 6-well plate. As a starting point, we recommend using 0.5 µg DNA and 5.0 pmols siRNA (final concentration 5.0 nM) per well of a 6-well plate which usually give satisfactory knockdown effect.

The following conditions are given per well of a 6 well plate. For other culture format, please refer to **Table 2**.

- For each well, add 1.0 ml of complete medium with serum and antibiotics freshly 30~60 minutes before transfection.
- Dilute 0.5 µg DNA and 5.0 pmols siRNA (final 5.0 nM) into 100 µl of working solution of PepMute™ Transfection Buffer. Vortex to mix followed by brief spin to bring drops to the bottom of the tube.

Note: For optimal transfection efficiency and maximum gene silencing, PepMute™ Transfection Buffer is a must for diluting siRNA/DNA and PepMute™ reagent. We strongly suggest preparing siRNA stock solution at 5.0 µM, so add 1.0 µl siRNA stock solution per well of 6-well plate to make final 5.0 nM of siRNA.

- Add 3 µl PepMute™ reagent immediately, mix by pipetting up and down.
- Incubate for ~15 min at RT to let transfection complex form.

Note: Never keep the complex longer than 30 minutes.

- Add the transfection complex to the cells drop wise.
- Gently rock the plate back and forth and return the plate to the incubator.
- Replace transfection medium by cell growth medium ~5 hours after transfection when necessary.
- Gene silencing is usually measured 24~48 hours post transfection.

Storage: PepMute™ siRNA Transfection Reagent is stable for up to 12 months at 4 °C. This item shipped at ambient temperature